

Standalone license installation and activation

Attention :

To install Phase Manager it is **highly recommended to have administrator rights**

1/ Installation of Phase Manager

Download Phase Manager. **Right click** on the executable than run it with **Administrator rights**


Once launched, choose the installation language:




Skip the welcome screen by clicking on **Next**:



Read then accept the license agreement to continue the installation by clicking on **Next**:



By default the setup will ask you to install Phase Manager in : **C:\Program Files (x86)\PhaseManager X**
If you didn't launch it with **admin right** , it will propose you to install Phase Manager in :
C:\Users\Public\Documents\PhaseManager7




Choose 'Single user installation'



Validate the Start Menu Folder screen by clicking on **Next**:



Choose and validate the icons creation screen by clicking **Next**:




On the following screen click on **Install** then once installation is complete, click on **Finish**

2/ Standalone license configuration

Once Phase Manager 5 is installed, double-click on its icon to launch it.

At first launch, the license configurator will display:



To activate your license, you will need to fill in the following fields:

Module

Choose **Monoposte | Standalone**

Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire:

- licence pattern : LPMM-00**NNN**0 **X** 00abcDEF (NNN is the number of your license, and X the version)
- **only paste the right part of your Product-ID, after the '-'**

Activation key

Fill in the Serial number sent to you by Projet Linéaire.

- pattern : VccQX-37eJG-AZIce-EYk7O-temCP-8DRFu

Licence


Choose “*Create new licence*”. By clicking on **Browse** you can choose the location of the license file that will be created by Phase Manager : **we recommend to leave the default value**.

3/ License activation


Click now on the button **Launch** to activate your licence.

Beware : an Internet connection is mandatory to activate the license !


To activate the license, switch to English then choose the option below and click on **Next**:



- Fill-in all required data then click on Next:
- **The Serial number is the Activation Key that's been used at step 2 in the license configurator**



- Check that you ARE connected to INTERNET then click on Next twice.
- If the following message is displayed, that means that Phase Manager did activate right. Click on Next to run Phase Manager:



- If you need to, feel free to contact our customer support at support@projetlineaire.com