

Standalone license installation and activation

Attention :

To install Phase Manager it is highly recommended to have administrator rights

1/ Installation of Phase Manager

Donwload Phase Manager. Right click on the executable than run it with Administrator rights

Once launched, choose the installation language:

×

Skip the welcome screen by clicking on Next:



Read then accept the license agreement to continue the installation by clicking on Next :

🦉 Setup - Phase Manager X.x —	×
License Agreement Please read the following important information before continuing.	ð
Please read the following License Agreement. You must accept the terms of this agreement before continuing with the installation.	
LICENSE OF USE SOFTWARE PHASE MANAGER Article 1 - Purpose of these terms and conditions The purpose of these general terms and conditions is to specify the conditions under which the PROJET LINEAIRE DEVELOPPEMENT EDITOR grants the USER a right to use the PHASE MANAGER SOFTWARE and ensures the maintenance of the said PHASE MANAGER SOFTWARE. Article 2 - Use of the PHASE MANAGER SOFTWARE The PHASE MANAGER SOFTWARE is for experienced or non-confirmed users working on a Windows environment only (Vista or higher). The USER tested the PHASE MANAGER SOFTWARE before signing the purchase order.	~
 I accept the agreement I do not accept the agreement 	
< Back Next >	Cancel

By default the setup will ask you to install Phase Manager in : C:\Program Files (x86)\PhaseManager X If you didn't launch it with admin right, it will propose you to install Phase Manager in : C:\Users\Public\Documents\PhaseManager7

🤹 Setup - Phase Manager X.x	_		\times
Select Destination Location Where should Phase Manager be installed?			
Setup will install Phase Manager X.x into the following folder			
To continue, click Next. If you would like to select a different folder,	click Br	owse.	
C:\Program Files (x86)\PhaseManager X.x	B	rowse	
At least 848,7 MB of free disk space is required.			
< Back Next	>	Ca	incel

Choose 'Single user installation'

×

Validate the Start Menu Folder screen by clicking on Next:

×

Choose and validate the icons creation screen by clicking *Next* :

Select the additional tasks you would like Setup to perform while installing Phase Manager X.x, then click Next.
Additional icons:
Create a desktop icon
Create a Quick Launch icon

On the following screen click on Install then once installation is complete, click on Finish

2/ Standalone license configuration

Once Phase Manager 5 is installed, double-click on its icon to launch it. At first launch, the license configurator will display:

😵 Phase Manager Launcher		- 🗆 X	
Licence System Java System			
A Phase Manager		Licensing Configuration	
Phase Manager	Module	Monoposte 👻	
Scheduled construction PHASE MAPS	Product ID	LPMM Your Product ID	
Licence	Activation Key	Your activation key (serial number)	
& Licensing	Create new licence Choose a licence		
	Browse	C:\Users\Public\Documents\PhaseManager-Licence	
Settings			
		Launch	

To activate your license, you will need to fill in the following fields:



Module

Choose Monoposte | Standalone

Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire:

- licence pattern : LPMM-00NNN0 X 00abcDEF (NNN is the number of your license, and X the version)
- only paste the right part of your Product-ID, after the '-'

Activation key

Fill in the Serial number sent to you by Projet Linéaire.

• pattern : VccQX-37eJG-AZIce-EYk7O-temCP-8DRFu

Licence

Choose "*Create new licence*". By clicking on **Browse** you can choose the location of the license file that will be created by Phase Manager : **we recommend to leave the default value**.

3/ License activation

Click now on the button Launch to activate your licence.

Beware : an Internet connection is mandatory to activate the license !

To activate the license, switch to English then choose the option below and click on Next:





- Fill-in all required data then click on Next:
- The Serial number is the Activation Key that's been used at step 2 in the license configurator



Activation of PhaseManager	×
	Please enter the activation data
	E <mark>nter S</mark> erial Number
Please enter all required information for the activation process.	Be sure to have the same Serial number (Activation key) as used earlier
	Where do you find your Serial Number?
	Enter Name / Company / Organisation
	Your company name
	Enter your E-mail Address
	your E-mail address
le.	required
② English	Back Next End

- Check that you ARE connected to INTERNET then click on Next twice.
- If the following message is displayed, that means that Phase Manager did activate right. Click on Next to run Phase Manager:





• If you need to, feel free to contact our customer support at support@projetlineaire.com