

## Installation and Network license activation

### Caution:

- 1/ 1/ The activation of the network license must only be done once! All workstations that then want to use the license should refer to the procedure: [Connection to a network license](#)
- 2/ To install Phase Manager it is **highly recommended to have administrator rights**
- 3/ To use the license it is necessary to **MODIFY rights on the UNC license directory**

### 1/ Installation of Phase Manager

Download Phase Manager. **Right click** on the executable than run it with **Administrator rights**


Once launched, choose the installation language:



Skip the welcome screen by clicking on **Next**:




Read then accept the license agreement to continue the installation by clicking on **Next**:



**By default** the setup will ask you to install Phase Manager in : **C:\Program Files (x86)\PhaseManager X**

**If you didn't launch it with admin right** , it will propose you to install Phase Manager in :

**C:\Users\Public\Documents\PhaseManager7**




Choose '**Single user installation**'



Validate the Start Menu Folder screen by clicking on **Next** :



Choose and validate the icons creation screen by clicking **Next** :




On the following screen click on **Install** then once installation is complete, click on **Finish**

## 2/ Network license Activation

Once Phase Manager is installed, double-click on its icon to launch it.

At first launch, the license configurator will display:

To activate your network license, you will need to fill in the following fields:



## Module

Choose Network | Réseau:

## Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire or reseller:

- licence pattern : LPMM-00NNN0 X 00abcDEF (NNN is the number of your license, and X the version)
- only paste the right part of your Product-ID, after the '-' :

## Activation key

Fill in the Serial number sent to you by Projet Linéaire or reseller.

## Licence

Choose "Create new licence".

By clicking on the button **Browse** you can choose the location of the license file that will be created by Phase Manager:


Indicate a UNC path using the following pattern : **\SERVER\_NAME\SHARE\FOLDER:**

### 3/ License activation


Click now on the button **Launch** to activate your licence.

**Beware : an Internet connection is mandatory to activate the license !**


To activate the license, switch to English then choose the option below and click on **Next** :



- Fill-in all required data then click on Next:
- **The Serial number is the Activation Key that's been used at step 2 in the license configurator**



- Check that you ARE connected to INTERNET then click on Next twice.
- If the following message is displayed, that means that Phase Manager did activate right. Click on Next to run Phase Manager:



- If you need to, feel free to contact our customer support at [support@projetlineaire.com](mailto:support@projetlineaire.com)