

## Installation and Network license activation

### Caution:

1/ 1/ The activation of the network license must only be done once! All workstations that then want to use the license should refer to the procedure: [Connection to a network license](#)

2/ To install Phase Manager it is **highly recommended to have administrator rights**

3/ To use the license it is necessary to **MODIFY rights on the UNC license directory**

### 1/ Installation of Phase Manager

Download Phase Manager. **Right click** on the executable than run it with **Administrator rights**


Once launched, choose the installation language:




Skip the welcome screen by clicking on **Next** :



Read then accept the license agreement to continue the installation by clicking on **Next** :



**By default** the setup will ask you to install Phase Manager in : **C:\Program Files (x86)\PhaseManager X**  
**If you didn't launch it with admin right** , it will propose you to install Phase Manager in :  
**C:\Users\Public\Documents\PhaseManager7**




Choose '**Single user installation**'



Validate the Start Menu Folder screen by clicking on **Next** :



Choose and validate the icons creation screen by clicking **Next** :




On the following screen click on **Install** then once installation is complete, click on **Finish**

---

## 2/ Network license Activation

Once Phase Manager is installed, double-click on its icon to launch it.  
At first launch, the license configurator will display:

To activate your network license, you will need to fill in the following fields:



The screenshot shows the 'Phase Manager Launcher' window. It has two tabs: 'Licence System' (selected) and 'Java System'. The main area is titled 'Licensing Configuration'. On the left, there is a large graphic with the Phase Manager logo and the text 'Licence & Licensing Configuration Settings'. The configuration fields are as follows:

- Module:** A dropdown menu with 'Reseau' selected.
- Product ID:** A text field containing 'LPMP' and a placeholder 'your product ID'.
- Activation Key:** A text field with the placeholder 'Your activation key (serial number)'.
- License Selection:** Two radio buttons: 'Create new licence' (selected) and 'Choose a licence'.
- Browse:** A button next to a text field containing the placeholder 'the path to the folder on the server'.

A 'Launch' button is located at the bottom right of the window.

## Module

Choose **Network | Réseau**:

## Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire or reseller:

- licence pattern : LPMM-00NNN0 X 00abcDEF (**NNN** is the number of your license, and **X** the version)
- **only paste the right part of your Product-ID, after the '-' :**

## Activation key

Fill in the Serial number sent to you by Projet Linéaire or reseller.

## Licence

Choose "Create new licence".

By clicking on the button **Browse** you can choose the location of the license file that will be created by Phase Manager:


Indicate a UNC path using the following pattern : **\\SERVER\_NAME\SHARE\FOLDER:**

### 3/ License activation


Click now on the button **Launch** to activate your licence.

**Beware : an Internet connection is mandatory to activate the license !**

To activate the license, switch to English then choose the option below and click on **Next** :



- Fill-in all required data then click on Next:
- **The Serial number is the Activation Key that's been used at step 2 in the license configurator**



Activation of PhaseManager

Please enter the activation data

Please enter all required information for the activation process.

**Enter Serial Number**

Be sure to have the same Serial number (Activation key) as used earlier

[Where do you find your Serial Number?](#)

**Enter Name / Company / Organisation**

Your company name

**Enter your E-mail Address**


your E-mail address

required

English

Back Next End

- Check that you ARE connected to INTERNET then click on Next twice.
- If the following message is displayed, that means that Phase Manager did activate right. Click on Next to run Phase Manager:



- If you need to, feel free to contact our customer support at [support@projetlineaire.com](mailto:support@projetlineaire.com)